





Installation



a. Connect the cradle

- » Turn on the stock recorder by pressing and holding the power button.
- » Place the stock recorder firmly in the cradle.
- » Attach the two cords in the back of the cradle.
- » Plug the power cord into a wall socket.
- » Plug the USB cord into a USB port on your computer. The green light on the Psion stock recorder should start to flash.



b. Install the program on your computer

- » Insert the FarmWorks by SDL disk into the CD drive.
- » The installation screen should open automatically.
- » Click once on **Install/Upgrade Stock Recorder**.
- » Windows Mobile Device Center will start to install.
- » Click **Continue** on the compatibility warning screen.
- » Click **OK** when the installation is finished.
- » Close all the installation screens.



Installation




a. Windows Mobile Device Center is the program that links your stock recorder to FarmWorks on the computer. You must set up a partnership between the computer and the stock recorder so they can communicate.


- » After installation you should see the Windows Mobile Device Center screen. If not, eject the stock recorder from the cradle, then push it back in again.
- » Select **Set up your device**




- » “How many computers should your device sync with?” Select **Yes** - one computer.
- » Click on **Next**.



- » “What kind of items do you want to sync?” None - untick all the boxes.



- » “Ready to set up a Windows Mobile partnership”
 - Type in a name for your Psion stock recorder
 - Select “Merge the existing items on the device...”
- » Click on **Set up**.





Installation

- a. Look for the big green tick that shows your stock recorder is connected.

IMPORTANT!


You cannot use your stock recorder until you have sent your farm details from FarmWorks. Read the stock recorder Quick Start guide or refer to page 10 of this manual to learn how to do a data transfer.



Trouble-shooting

If you can't find the Windows Mobile Device Center -

- » It might be called "Sync Center" instead.
- » Use Windows Explorer to search - click on the Start button, type in *Windows Mobile*



If the stock recorder won't connect -

- » Pop the stock recorder out of the cradle. Check the copper connector plates on the bottom are clean, then push the stock recorder firmly back into the cradle.
- » *Are the cords attached correctly?* The cradle must be connected to the computer with the USB cord.
- » *Is the stock recorder turned on?* It must be 'awake' and in the cradle.
- » *Is there a message window hiding on the screen that's waiting for a response?* Look around on the desktop or down on the bottom taskbar; close the message box and the stock recorder will connect.